

Document Details			
Organization 單位名稱	匯智資訊股份有限公司		
Document 文件名稱	WIS 匯智-預覽網頁使用說明_Host 指向		
Document 文件種類	WEB	Date 日期	2009-06-30



預覽網頁使用說明_Host 指向

STEP1 : 開始 → 執行 → 輸入 notepad \WINDOWS\system32\drivers\etc\hosts



Document Details			
Organization 單位名稱	匯智資訊股份有限公司		
Document 文件名稱	WIS 匯智-預覽網頁使用說明_Host 指向		
Document 文件種類	WEB	Date 日期	2009-06-30



STEP2：輸入 IP 空一格 網址，按儲存即可開啓 IE 瀏覽網頁。

```

hosts - 記事本
檔案(F) 編輯(E) 格式(O) 檢視(V) 說明(H)
# Copyright (c) 1993-1999 Microsoft Corp.
#
# This is a sample HOSTS file used by Microsoft TCP/IP for Windows.
#
# This file contains the mappings of IP addresses to host names. Each
# entry should be kept on an individual line. The IP address should
# be placed in the first column followed by the corresponding host r
# The IP address and the host name should be separated by at least c
# space.
#
# Additionally, comments (such as these) may be inserted on individu
# lines or following the machine name denoted by a '#' symbol.
#
# For example:
#
#      102.54.94.97      rhino.acme.com          # source server
#      38.25.63.10     x.acme.com             # x client host

127.0.0.1      localhost
主機IP Domain name 先輸入主機IP，空一格，再輸入網址名稱。
12.23.34.56 www.abc.com | ← 範例

```

STEP3：預先瀏覽完畢無誤後，即可重覆以上一步驟，將二步驟輸入的資料刪除儲存即可

```

#
#
# Additionally, comments (such as these) may be inserted on individual
# lines or following the machine name denoted by a '#' symbol.
#
# For example:
#
#      102.54.94.97      rhino.acme.com          # source server
#      38.25.63.10     x.acme.com             # x client host

127.0.0.1      localhost
|

```